

MapleSim Server Administrator Guide

**Copyright © Maplesoft, a division of Waterloo Maple Inc.
2021**

MapleSim Server Administrator Guide

Copyright

Maplesoft, MapleSim Server and Maple are all trademarks of Waterloo Maple Inc.

© Maplesoft, a division of Waterloo Maple Inc. 2021. All rights reserved.

No part of this book may be reproduced, stored in a retrieval system, or transcribed, in any form or by any means — electronic, mechanical, photocopying, recording, or otherwise. Information in this document is subject to change without notice and does not represent a commitment on the part of the vendor. The software described in this document is furnished under a license agreement and may be used or copied only in accordance with the agreement. It is against the law to copy the software on any medium except as specifically allowed in the agreement.

Oracle, Java and all Java-based marks are trademarks or registered trademarks of Oracle and/or its affiliates. Docker is a registered trademark of Docker, Inc.

All other trademarks are the property of their respective owners.

This document was produced using Maple and DocBook.

Contents

Overview	v
1 Basics of Running MapleSim Server	1
1.1 Glossary of Variables Used in This Chapter	1
1.2 Loading the MapleSim Server Docker Image	1
1.3 Starting MapleSim Server	1
Starting MapleSim Server Using the docker run Command	1
Starting MapleSim Server Using a docker compose File	2
Replacing the Landing Page	3
1.4 Stopping MapleSim Server	3
1.5 Removing a Docker Image	3
1.6 Adding Content to MapleSim Server	3
1.7 MapleNet Logging	3
docker log	4
MapleNet options	4
2 Environment Variable Configuration	5
2.1 Licensing	5
2.2 Directory Setup	5
2.3 Managing Connections	5
2.4 Directory Listings	6
2.5 Sendfile Usage	6
2.6 Content Delivery Network	6
2.7 Worksheet Template Location	6
2.8 Web Server Endpoints	7
2.9 CORS	7
2.10 SSL	8
2.11 Client Configuration	8
2.12 Managing Maple Engines	9
2.13 Maple Configuration	10
2.14 Configuring Logging	11
2.15 Data Limit	11
2.16 Compute Engine	11
2.17 Document Engine	12
3 Security Issues	15
3.1 Untrusted Users	15
3.2 Trusted Users	15
4 MapleNet Metrics and Monitoring	17
4.1 Metrics and Monitoring Tools	17
Health Check	17
Monitoring	18
Metrics over Prometheus	19
5 Example Configurations	23
5.1 Basic Document Hosting	23
Mounting as a subdirectory of /webroot	23
Mounting on top of /webroot	24
Using a Content Delivery Network for JavaScript libraries	24
Logging Configuration	25
5.2 Basic Compute Hosting	25
Cross-Origin Resource Sharing (CORS)	25
5.3 Adding Maple Libraries and Help Databases	26
Changing the URL for the Help Database	26
5.4 Enabling the Upload Page	27

5.5 Security Options	27
5.6 Troubleshooting	28
Docker not starting	28
MapleNet is not starting	28
Performances Issues	29
6 Copyright	31
6.1 Client Side Software Copyright Statements	31
error_prone_annotations	31
j2objc-annotations 1.3	31
guava 23.0	31
guava-gwt 23.0	31
gwtquery 1.5 beta 1	31
gwtexporter 2.5.0	31
eventbinder 1.10	31
akjava	31
gwt-log 3.3.2	31
GWT 2.8.1	31
6.2 Server Side Software Copyright Statements	32
Maple Licensed Code	32
Open Source	33
Font Licenses	46
MapleSim Open Source	47
Index	57

Overview

About MapleSim Server

MapleSim Server provides an easy web deployment option for your MapleSim-based solutions. The MapleSim Server allows engineers throughout your organization to explore MapleSim simulation models from a web browser, even if they do not have MapleSim.

Docker Container for MapleSim Server

The MapleSim Server server is intended to be deployed in the Docker container generated by the MapleSim Server installer. Running it requires the Docker container engine. We recommend using the latest stable release of Docker. The Docker container contains all the dependencies of the MapleSim Server binary. The Docker container can also be deployed to various cloud hosting environments.

For more information on where to obtain the Docker engine for your platform, installing MapleSim Server and running the MapleSim Server container see the **MapleSim Server Installation Guide**.

Note: Attempting to run MapleSim Server outside of the Docker container is not supported.

MapleSim Server Resources

Since MapleSim Server is built on and shares much of its content with MapleNet (including APIs), some additional documentation is listed below to help you further explore MapleNet.

Resource	Description
MapleSim Server Installation Guide	System requirements and installation instructions for MapleSim Server. The MapleSim Server Installation Guide is available in the Install.html file located either on your MapleSim Server installation DVD or the folder where you installed MapleSim Server.
MapleNet Services Guide	Outline of MapleNet services. Information on limitations of services provided as well as a summary of MapleNet API endpoints.
MapleNet API Programming Guide	A detailed description of the MapleNet API with examples.

For additional resources, visit http://www.maplesoft.com/site_resources.

Getting Help

To request customer support or technical support, visit <http://www.maplesoft.com/support>.

Customer Feedback

Maplesoft welcomes your feedback. For comments related to the MapleSim Server product documentation, contact doc@maplesoft.com.

1 Basics of Running MapleSim Server

1.1 Glossary of Variables Used in This Chapter

The following variables are used in this chapter, and should be replaced with the correct values:

SIMLICENSEFILE: The location of the MapleSim license file (on the host machine).

LICENSEFILE: The location of the MapleNet license file (on the Docker host)

HOSTPORT: The port on the host machine on which MapleNet should accept connections

IMAGETAG: The tag of the Docker image created by the installer

CONTENTDIR: The directory containing content for hosting by MapleSim Server (on the Docker host)

MAPLEONLINECDNURL: The URL of a Content Delivery Network hosting the MapleNet JavaScript libraries

MATHJAXCDNURL: The URL of a Content Delivery Network hosting the Math Jax JavaScript package

HOSTADDRESS: Is either the ip address or machine address of the machine running the MapleSim Server Docker container

CONTAINERID: The container id obtained from running `docker container ls`

Additional documentation for the configuration variables used in these examples is available in the Configuration section of the Administrators Guide

1.2 Loading the MapleSim Server Docker Image

After you have installed MapleSim Server, you must load the MapleSim Server image into Docker.

To load the MapleSim Server image:

1. Open a command prompt and navigate to the MapleSim Server installation folder, before running this command.
2. Run the following command:

```
docker load --input MapleSimServer-2021.1.tar
```

Note: This process could take several minutes.

Next, find the MapleSim Server container image tag using the command:

```
docker images.
```

You are now ready to start MapleSim Server.

1.3 Starting MapleSim Server

Starting MapleSim Server Using the docker run Command

To start MapleSim Server, run the following Docker command:

```
docker un --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly  
--mount type=bind,source=$SIMLICENSEFILE,target=/maple/toolbox/MapleSim/license/MapleSim.dat,readonly
```

```

--mount type=bind,source=$CONTENTDIR,target=/webroot/content
--publish $HOSTPORT:8080
--rm -e MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING=true maplesoft/maplesimserver:$IMAGETAG

```

(1.1)

In this example:

```

$LICENSEFILE           =      "/home/qa/maplenet/2021.1/license/license.dat"
$SIMLICENSEFILE        =      "/home/qa/maplenet/2021.1/license/license.dat"
$CONTENTDIR            =      "/home/qa/Desktop/Worksheets"
$HOSTPORT              =      8080
$IMAGETAG              =      2019.2-1460361

```

Note: If \$LICENSEFILE contains spaces, then you must enclose the path in quotation marks. For example, source="C:\Program Files\MapleNet\2021\license.dat".

To test if MapleSim Server is running properly navigate to `http://$HOSTADDRESS:8080` in your browser.

You should see a page displayed with a link to a Maple demo worksheet.

For more information on using the `docker run` command, see <https://docs.docker.com/engine/reference/command-line/run/>

Starting MapleSim Server Using a docker compose File

Alternatively, you can specify MapleSim Server options using a docker compose (YAML) file:

```

version: 3.7

services:
  maplesimserver:
    image: maplesoft/maplesimserver:$IMAGETAG
    ports:
      - "$HOSTPORT:8080"
    volumes:
      - type: "bind"
        source: $LICENSEFILE
        target: "/maple/license/license.dat"
        read_only: true
      - type: "bind"
        source: $SIMLICENSEFILE
        target: "/maple/toolbox/MapleSim/license/MapleSim.dat"
        read_only: true

```

The command used to deploy MapleSim Server is

```
docker stack deploy maplenet --compose-file <path to above file>
```

To test if MapleSim Server is running properly navigate to `http://$HOSTADDRESS:8080` in your browser.

You should see a page displayed with a link to a Maple demo worksheet.

For more information on the `docker stack` command, see <https://docs.docker.com/engine/reference/command-line/stack/>.

For more information on docker compose files, see <https://docs.docker.com/compose/gettingstarted/>

Replacing the Landing Page

The MapleSim Server container, by default, includes a landing page, *index.html*. Located at the bottom of the MapleSim Server file directory. To replace this page, mount a directory from your host machine, with the replacement landing page (called *index.html*) onto your MapleSim Server Docker container, mapping it to the directory containing your current *index.html* file. For more information on mounting host machine directories into the MapleSim Server Docker container, see *Basic Document Hosting (page 23)*.

1.4 Stopping MapleSim Server

To stop the MapleSim Server:

1. At the prompt, to list your running containers, enter:

```
docker container ls
```

Find the running MapleSim Server container ID in the list.

2. Next, you must stop the MapleSim Server Docker container. To do this, enter:

```
docker container stop $CONTAINERID
```

Where *\$CONTAINERID* is the container id obtained from step 1.

For more information on the docker stop command see <https://docs.docker.com/engine/reference/commandline/stop/>

1.5 Removing a Docker Image

At some point, you may want to remove some docker images from your machine.

To remove a Docker image, enter:

```
docker image rm $IMAGETAG
```

For more information on the `docker image` command, see:

<https://docs.docker.com/engine/reference/commandline/image/>

1.6 Adding Content to MapleSim Server

MapleSim Server is capable of rendering both classic and standard Maple worksheets, and Maple workbooks, as well as MapleSim models, for display in a web browser. This is the easiest way to create web content for use with MapleSim Server. Placing content in the correct location on MapleSim Server makes the content available to users. Without an installed copy of Maple, users can interact with a posted worksheet using their web browser, and even perform new computations.

For instructions and examples on how to configure MapleNet to host Maple documents, see the *Basic Document Hosting (page 23)*.

1.7 MapleNet Logging

MapleNet is a server process and as such it generates informative logs by default. It is important to understand how MapleNet logging working so its logs can be properly maintained and used.

docker log

MapleNet is deployed as a Docker container therefore its logs are captured by docker. You can access these logs by using the `docker logs` command. Docker has extensive logging configuration options for how it maintains its logs and for sending docker logs to other logging systems. You can also add command line arguments to the `docker run` command to configure how docker maintains MapleNet's logs. See *Logging Configuration (page 25)* for a basic log configuration example. For more information about docker's logging options, see

docker log: <https://docs.docker.com/engine/reference/commandline/logs/>

docker log driver configuration: <https://docs.docker.com/config/containers/logging/configure/>

MapleNet options

MapleNet has various options for configuring the generated logs. All these options are documented in the Configuration section. The most important option is the `MAPLENET_LOGGING_LEVEL` option. This option controls how verbose MapleNet's logging is. This options accepts the following values (from most verbose to quietest): `trace`, `debug`, `info`, `warning`, `error`, `fatal`. The default logging level is `info`. This level is chosen to provide a balance of informative logging without being excessive. Increasing the logging to `debug` or `trace` will provide additional logging, however these additional log are intended for developers more than users. Decreasing the logging levels will reduce the amount of information which may seem desirable, however should something go wrong, the reduced logging means less information for determining what happened. The default level (`info`) is the suggested level for a normal MapleNet deployment. If log storage is a concern, it is better to configure the docker log driver with log rotation than to decrease the logging level of MapleNet.

2 Environment Variable Configuration

As MapleNet is deployed as a Docker container, configuration is handled by setting environment variables within the Docker container. On the Docker command line (`docker run`) you can set an environment variable by using the `-e` command line argument. They can also be specified in a Docker stack YAML file. Any variables that are used to specify files or directories are for locations are **within** the container. See the *Adding Maple Documents to MapleNet* section of this guide for information on adding content to the Docker container.

The environment variables all start with the `MAPLENET_` prefix.

2.1 Licensing

Environment Variable	Parameter	Description
<code>MAPLENET_LICENSE</code>	file	This variable specifies which license file MapleNet uses. The license file must exist within the container at the time that MapleNet starts. It must be added to the container or mounted into the container.

2.2 Directory Setup

Environment Variable	Parameter	Description
<code>MAPLENET_WEBSERVER_DOCUMENTROOT</code>	directory	This variable specifies which directory MapleNet uses as its document root, the base directory of the content hosted by MapleNet. The default value of document root is <code>/webroot</code> . To make content available to users, mount a directory containing the content under the container's <code>/webroot</code> directory.
<code>MAPLENET_WEBSERVER_CACHEDIR</code>	directory	This variable specifies the directory where MapleNet stores cache files. The default value of this variable is <code>/webroot/maplenet/cache</code> . Cache directories contain temporary files required for rendering documents. As the remote clients need access to files in the cache directories, the cache directories must be located under document root.

2.3 Managing Connections

Environment Variable	Parameter	Description
<code>MAPLENET_WEBSERVER_REQUESTTIMEOUTMS</code>	timeout in milliseconds	This variable specifies how long, in milliseconds, MapleNet waits before timing out connections. The default value of this variable is 30000 (30 seconds). Documents that are opened by users will periodically connect to MapleNet to make sure those connections are kept open. This timeout is mostly for cases where clients disconnect without properly closing their connection.
<code>MAPLENET_WEBSERVER_NUMTHREADS</code>	integer	This variable specifies the maximum number of threads MapleNet can use for accepting connections. The default value is 1024. These threads are used to handle user connections. If all of these threads are used, MapleNet will not be able to accept new connections.

MAPLENET_WEBSERVER_NOTFOUNDFILE	file	This variable specifies a file to be sent to the user when a requested file cannot be found. The default is the <i>empty string</i> , which causes MapleNet to reply with a very simple 404 message.
MAPLENET_WEBSERVER_PORT	port number	This variable specifies the port MapleNet listens on for new connections. The default value of this variable is 8080. This is the port within the Docker container. You will still need to map this port to an external port on the host machine, thus changing this is generally not required.

2.4 Directory Listings

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING	boolean	This variable specifies whether MapleNet permits directory listings. The default value of this variable is <i>false</i> . Directory listings allow the user to navigate document root like a file system.

2.5 Sendfile Usage

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_ENABLESENDFILE	boolean	This variable specifies whether MapleNet uses the <i>sendfile</i> command to optimize file transfers. <i>By default this option is enabled.</i> In some host configurations (certain networked or virtualized file systems) using <i>sendfile</i> can lead to data corruption in the transferred file.

2.6 Content Delivery Network

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_MAPLECLLOUDCDN	URL	This variable specifies the base URL to use for fetching the MapleNet JavaScript library. The default value for this variable is <i>"/mapleonline"</i> , meaning the library will be loaded from the <i>mapleonline</i> subdirectory of MapleNet's document root. This can be used to place the library (<i>mapleonline.nocache.js</i>) on to a Content Delivery Network (CDN). <i>mapleonline.nocache.js</i> will be appended to the given URL.

2.7 Worksheet Template Location

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_MAPLEWORKSHEET	filename	This variable specifies the file to use as the Worksheet HTML template page. By default, this file is

		/maple/data/MapleWorksheet.html. Some users may want to use a custom version of this file.
--	--	---

2.8 Web Server Endpoints

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_ENDPOINTS_COMPUTE	boolean	This variable specifies whether MapleNet enables its compute endpoint. The default value of this variable is <code>true</code> . The compute endpoint allows for a user to submit a Maple computation request to the server and receive the result as a reply.
MAPLENET_WEBSERVER_ENDPOINTS_DOCUMENT	boolean	This variable specifies whether MapleNet enables its document endpoint. The default value of this variable is <code>true</code> . The document endpoint allows for users to open Maple worksheets hosted by MapleNet in a browser.
MAPLENET_WEBSERVER_ENDPOINTS_DOWNLOAD	boolean	This variable specifies whether MapleNet permits users to download the Maple documents hosted by MapleNet. The default value of this variable is <code>false</code> . If set to <code>true</code> , adding the <code>download url</code> parameter to the url of a Maple document causes it to be downloaded instead of displayed.
MAPLENET_WEBSERVER_ENDPOINTS_HELP	boolean	This variable specifies whether MapleNet enables its help endpoints. The default value of this variable is <code>true</code> . The help endpoints allow users to display worksheets taken from a Maple help database.
MAPLENET_WEBSERVER_ENDPOINTS_UPLOAD	boolean	This variable specifies whether MapleNet enables the upload endpoint. The default value is <code>false</code> . Enabling the upload endpoint allow users to upload content to MapleNet using the <code>upload.html</code> page.

2.9 CORS

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_CORS_ALLOWORIGIN	string	This variable specifies the value MapleNet sets for the cross-origin resource sharing (CORS) allow origin header. The default value for this value is the <i>empty string</i> . CORS allows sites hosted on different domains to access resources from MapleNet.
MAPLENET_WEBSERVER_CORS_ALLOWMETHODS	string	This variable specifies the value MapleNet sets for the cross-origin resource sharing (CORS) allow methods header. The default value for this value is the <i>empty string</i> . CORS allows sites hosted on different domains to access resources from MapleNet.
MAPLENET_WEBSERVER_CORS_ALLOWHEADERS	string	This variable specifies the value MapleNet sets for the cross-origin resource sharing (CORS) allow headers header. The default value for this value is the <i>empty string</i> . CORS allows sites hosted on different domains to access resources from MapleNet.

2.10 SSL

Environment Variable	Parameter	Description
MAPLENET_WEBSERVER_SSL_VERIFYPEER	boolean	This variable specifies that MapleNet will require that connecting clients have a valid certificate. The default value of this variable is <code>false</code> . This allows the server to verify that any connecting client has a certificate that is signed by certificate authority from the server's trusted certificate authorities.
MAPLENET_WEBSERVER_SSL_CAPATH	directory	This variable specifies a directory MapleNet will use as its certificate authority (CA) path. The default value of this variable is the <i>empty string</i> , meaning no CA path will be added. This directory will be searched for CA certificates in PEM format.
MAPLENET_WEBSERVER_SSL_CAFILE	file	This variable specifies a file MapleNet will use as its certificate authority (CA) file. The default value for this variable is the <i>empty string</i> , meaning no CA file will be added. A CA file is a file containing CA certificates in PEM format.
MAPLENET_WEBSERVER_SSL_VERIFYDEPTH	integer	This variable specifies the maximum depth of a certificate authority chain that MapleNet will accept. The default value for this variable is 9.
MAPLENET_WEBSERVER_SSL_DEFAULTVERIFYPATHS	boolean	This variable specifies whether MapleNet uses default values for <code>CAFILE</code> and <code>CAPATH</code> . The default is <code>true</code> . With this set MapleNet server will use default, OS supplied, certificates.
MAPLENET_WEBSERVER_SSL_CIPHERLIST	comma separated list or ALL	This variable specifies which ciphers MapleNet should present to clients for use with SSL. The default value for this variable is <code>ALL</code> , meaning all available ciphers should be presented.
MAPLENET_WEBSERVER_SSL_PROTOCOLVERSION	integer	This variable specifies the minimal version of SSL/TLS MapleNet will accept for connections. The default value for this variable is 0.
MAPLENET_WEBSERVER_SSL_SHORTTRUST	boolean	This variable specifies whether MapleNet checks for new certificates while it is running. The default value for this variable is <code>false</code> . When set to <code>true</code> MapleNet will check for new certificates added to the <code>CAFILE</code> or <code>CAPATH</code> .

2.11 Client Configuration

Environment Variable	Parameter	Description
MAPLENET_WEBCLIENT_CONFIGURATION	key=value	This variable is used to set client configuration values in MapleNet. The default value for this variable is the <i>empty string</i> (no values set). These key,value pairs are placed into a JavaScript map in the <code>MapleWorksheet.html</code> template. These values can then be accessed by JavaScript running in that page. The default MapleNet JavaScript currently recognizes the <code>MathJaxCDN</code> key. The corresponding value is the base URL to use for locating the MathJax library. When <code>MathJaxCDN</code> is not set, the MathJax library is loaded from the MathJax sub-directory of MapleNet's document root. This can be used to place the MathJax library on to a Content Delivery Network (CDN). <code>MathJax.js</code> will be appended to the given URL.
MAPLENET_WEBCLIENT_ADDITIONALJAVASCRIPTURL	string	This variable specifies a string that will be injected into the HTML page sent to the client when opening a document. The default value for this variable is the <i>empty string</i> , which mean that nothing will be added to the page. This can be used to add custom JavaScript to the page as viewed by the client.
MAPLENET_WEBCLIENT_HELPURL	URL	This variable sets a URL that that is used to map help links in worksheets to web pages. The default value for this variable is <code>/help/display</code> . The help topic from the help link is appended to this value to form the URL for the link. The default value maps the help links to the help endpoint of the server hosting the worksheet. Assuming the help page exists in the help databases and the help endpoints are enabled, then the help page should display.

2.12 Managing Maple Engines

Environment Variable	Parameter	Description
MAPLENET_POOL_MAXENGINES	integer	This variable sets the maximum number of Maple engines that MapleNet will start. The default value for this variable is 0, meaning no limit. This value is

		different than <code>MAPLENET_POOL_MAXRUNNINGENGINES</code> , as this limits the total number of engines that can be opened, not the number of running engines.
<code>MAPLENET_POOL_MAXFALLBACKENGINES</code>	integer	This variable sets the maximum number of Maple engines that MapleNet will start for image plot generation. The default value for this variable is 0, meaning no limit. The pool of engines for image plot generation is separate from the pool for normal computation/document engines.
<code>MAPLENET_POOL_COMPUTATIONTIMELIMIT</code>	seconds	This variable sets the timelimit for compute requests (as opposed to document computations). The default value is 360 seconds. Compute requests that run for longer than this will be stopped by MapleNet and an error will be returned.
<code>MAPLENET_POOL_DOCUMENTCOMPUTATIONTIMELIMIT</code>	seconds	This variable sets the timelimit for computations related to an open document (worksheet/workbook). The default value is 1200 seconds. Computations that last longer than this will be stopped by MapleNet and an error will be returned.
<code>MAPLENET_POOL_QUEUETIMELIMIT</code>	seconds	This variable sets the timelimit for requests (computation or document) that are not able to run because MapleNet is not allowed to start a running engine. The default value for this variable is 60 seconds. An engine may not be available to run because of limits on the number of running engines. For example license restrictions or <code>MAPLENET_POOL_MAXRUNNINGENGINES</code> . If a request waits longer than this limit, the request will be cancelled and an error will be returned.
<code>MAPLENET_POOL_MAXRUNNINGENGINES</code>	integer	This variable sets the maximum number of running engines that MapleNet will allow. It defaults to 0, which means the maximum allowed by the license. It is an error to set this value greater than the license allows.

2.13 Maple Configuration

Environment Variable	Parameter	Description
<code>MAPLENET_MAPLE_LIBRARY</code>	path	This variable specifies a value to set for the Maple libname variable. The default is the <i>empty string</i> , which uses the default value for Maple's libname. When specifying more than one path, use a comma (,) as a separator. When setting this parameter, only the directories listed will be used. If Maple's library (<code>maple.mla</code>) is not present in the list, MapleNet will not function properly.

MAPLENET_MAPLE_MSERVER	filename	This variable specifies the file to be executed when starting a Maple engine. The default value for this variable is the <i>empty string</i> . The default value uses the normal Maple engine binary.
------------------------	----------	---

2.14 Configuring Logging

Environment Variable	Parameter	Description
MAPLENET_LOGGING_DISABLE	boolean	This variable specifies if logging is disabled in MapleNet. The default value is <i>false</i> , meaning log messages will be generated.
MAPLENET_LOGGING_FILENAME	filename	This variable specifies a file that MapleNet's logs should be written to. The default value is the <i>empty string</i> . This default causes MapleNet to log to the console. Setting this value will capture the logs in a file within the Docker container. This is probably not what you want. Instead capture the output of Docker or use the <code>docker logs</code> command.
MAPLENET_LOGGING_FLUSH	boolean	This variable specifies if MapleNet should flush its logs whenever a logging message is produced. The default is <i>false</i> . Flushing causes log messages to not get buffered. This can reduce performance of MapleNet, but reduces the likelihood of a log message being lost if MapleNet should exit unexpectedly.
MAPLENET_LOGGING_LEVEL	log level	This variable specifies the logging level that MapleNet uses. There are 6 logging levels, from least to most output: <i>fatal</i> , <i>error</i> , <i>warning</i> , <i>info</i> , <i>debug</i> and <i>trace</i> . The default value is <i>info</i> , which generates sufficient logging for normal operations, without being excessive. Levels below <i>info</i> (<i>debug</i> and <i>trace</i>) are intended for debugging and generate too much output for normal use.
MAPLENET_LOGGING_SYNCHRONOUS	boolean	This variable whether MapleNet uses synchronous logging. The default is <i>false</i> . Synchronous logging forces the log messages to be generated directly by the caller, not send to another thread for output. This means the message is output more directly, reducing the likelihood the message will be lost if MapleNet exits unexpectedly.

2.15 Data Limit

Environment Variable	Parameter	Description
MAPLENET_ENGINE_JAVADATALIMIT	mebibytes	This variable specifies a data limit for Java operations used by MapleNet. The default is 2048 MiB. The Maple engine can utilize a Java virtual machine (JVM) for certain operations. This variable limits the maximum amount of memory the JVM is allowed to use.

2.16 Compute Engine

Environment Variable	Parameter	Description
MAPLENET_COMPUTEENGINE_COMMANDLINE	string	This variable specifies extra command line arguments to use when starting a Maple engine for the compute endpoint. The default value for this variable is the <i>empty string</i> .
MAPLENET_COMPUTEENGINE_DISABLESECURITY	boolean	This variable specifies whether MapleNet disables the security setting when starting a Maple engine for the compute endpoint.

		The default value for this variable is false. The Maple engine has security settings that restrict access to the operating system. Disabling the security setting will disable these restrictions, allowing Maple access to the entire system.
MAPLENET_COMPUTEENGINE_CPULIMIT	integer	This variable specifies whether MapleNet starts the Maple engines for the compute endpoint with a CPU limit. The default value for this variable is 0, which means no limit is given. Passing a CPU limit to the Maple engine halts the Maple engine after a the given number of CPU seconds. When setting a CPU limit, it is important to remember that compute engines are re-used a limited number of times and the CPU limit applies to the lifetime of the compute engine.
MAPLENET_COMPUTEENGINE_DATALIMIT	integer	This variable specifies whether MapleNet starts the Maple engines for the compute endpoint with a data limit. The default value for this variable is 0, which means no limit is given. Passing a data limit to the Maple engine limits the maximum amount of memory a Maple engine can access. If this limit is exceeded the Maple engine will shutdown. Compute engines are restarted between each computation, so each computation should start with a minimal amount of memory.

2.17 Document Engine

Environment Variable	Parameter	Description
MAPLENET_DOCUMENTENGINE_COMMANDLINE	string	This variable specifies extra command line arguments to use when starting a Maple engine for a document. The default value for this variable is the <i>empty string</i> .
MAPLENET_DOCUMENTENGINE_DISABLESECURITY	boolean	This variable specifies whether the MapleNet security setting is disabled when starting a Maple engine for a document. The default value for this variable is <code>false</code> . The Maple engine has security settings that restrict access to the operating system. Disabling the security setting will disable these restrictions, allowing Maple access to the entire system.
MAPLENET_DOCUMENTENGINE_CPULIMIT	integer	This variable specifies whether MapleNet starts the Maple engines for documents with a CPU limit. The default value for this variable is 0, which means no limit is given. Passing a CPU limit to the Maple

		engine halts the Maple engine after a certain number of CPU seconds. Document engines persist for the lifetime of the document, are not re-used. Thus this variable limits the total amount of CPU time a document session can consume.
MAPLENET_DOCUMENTENGINE_DATALIMIT	integer	This variable specifies whether MapleNet starts the Maple engines for the compute endpoint with a data limit. The default value for this variable is 0, which means no limit is given. Passing a data limit to the Maple engine limits the maximum amount of memory a Maple engine can access. If this limit is exceeded the Maple engine will shutdown. Document engines persist for the lifetime of the document, are not re-used. Thus this variable limits the total amount of memory a document session can consume.

3 Security Issues

MapleNet permits remote users to execute Maple code on a server. Maple is a full featured programming language, including tools for accessing the file system, networking and external calling to other programming language, such as Java, Python and C. It is difficult to restrict what users can access. Deploying MapleNet securely requires understanding the environment in which it is intended to be used. Do you trust your users, or is there a risk of malicious access? Are there users whose content should be kept private from others? This section will describe the security risks of deploying MapleNet server and best practices for limited harm.

3.1 Untrusted Users

The risk of allowing untrusted users to access MapleNet is that someone malicious might attempt to cause harm or exploit the system for their own purposes. It is difficult to secure MapleNet against malicious users so we advise against allowing untrusted users to access a MapleNet installation. The biggest risk is allowing an untrusted user to execute their own code. If you intend to deploy MapleNet where it would be accessible to untrusted users, we suggest the following procedures.

1. Configure MapleNet behind a load balancer with SSL offload.
2. Disable the compute endpoint. The compute endpoint explicitly allows users to run arbitrary Maple code on the server.
3. Disable the help endpoints. The help pages may contain examples that could be exploited.
4. Disable uploading. Another route to executing malicious code would be to embed it in a worksheet and upload it.
5. Disable directory listing. This makes it harder for malicious users to find content on the site.
6. Double-check your content. Maple worksheets can contain embedded components. These components can accept user input and cause Maple code to be evaluated. It is possible to create worksheets that execute Maple code entered into a component (a text area or math container, for example). Do not allow such worksheets to be hosted.
7. Make sure you have limited the CPU and data limits for your document engines. This makes denial of service attacks via Maple code more difficult.
8. Assume the content that users view is available to other users. With all the steps above implemented, it is very hard for one user to "snoop" on another user's content, however we suggest that you do not use MapleNet to display content that you would consider private when untrusted users have access to MapleNet.

3.2 Trusted Users

In an environment when you trust your users to not be malicious, MapleNet features can be enabled as you see fit. However there are still some issues to consider. Turning off unnecessary features is still a good idea. A curious user might experiment with the compute features of MapleNet without realizing it could negatively effect the performance of documents. With directory listings enabled, it is possible to locate temporary files created by on going computations and open documents (the contents of the cache directory). These locations can also be determined by viewing the HTTP requests made by a open document. These requests are encrypted when using SSL, but are sent in the clear when SSL is not enabled. This may be a concern as it allows one user to see some of the content generated by another user's document. If this is a concern, using SSL and disabling directory listings makes it significantly harder to discover those files. If you need to be certain that no data leakage can occur between groups of users, we suggest running multiple instances of MapleNet that are only accessible by users of the particular security levels.

4 MapleNet Metrics and Monitoring

4.1 Metrics and Monitoring Tools

MapleNet provides some secondary features and server monitoring tools. These are described below. The term endpoint refers to a URL that MapleNet provides that can be accessed using standard HTTP requests. When these endpoints are accessed MapleNet replies with an HTTP response containing the requested information. There is no file on the server corresponding to these replies, they are generated by MapleNet itself.

Health Check

The Health Check endpoint is `/healthcheck/`. When an `HTTP GET` accesses this endpoint MapleNet will reply with an HTTP response with a status code of 200 and with no content. This is intended to be used by monitoring services to verify that MapleNet is available. A successful reply from the health check endpoint verifies that MapleNet is able to accept new connections, but it does not verify that MapleNet is able to execute commands or open a new document.

The endpoint returns a json object of the form:

```
{
"check": "Foo",
"level": "WARNING",
"message": "Lorem ipsum dolor sit amet, consectetur adipiscing elit"
}
```

Where `check` is the name of the check that generated the message and `check` is one of:

- `PoolHeathCheck($poolName)`, where `$poolName` is one of `Document`, `Compute`, or `Fallback`
- `LicenseCheck`.

The `level` field is one of `OK`, `WARNING`, or `ERROR`.

It's important to note that `messages` is supposed to be an array.

The message is an arbitrary string providing feedback for the MapleNet administrator.

A successful health check won't produce any messages. A health check that is not successful will produce either a `WARNING` or an `ERROR` message, which will appear as an entry in the `messages`.

The most severe level of all the messages is put in the status field. If there are no messages, the status field is set to `OK`.

Status is one of `OK`, `WARNING`, or `ERROR`.

The http return code for a `GET` to `/healthcheck/` will be 200 if the status is `OK` or `WARNING`. An http return code of 500 is returned if the status is `ERROR`.

When the `healthcheck` endpoint is requested, the health checks that are exercised are:

- a license check
- exercising each kernel pool
- When each kernel pool is exercised, `2+3` is executed on each kernel. An error is returned if a kernel could not be retrieved from the pool or if the returned value is incorrect (in other words, if the answer is not 5). This could happen if the pools are already full and no kernels are released.

Command Line Parameter	Domain	Default	Purpose
<code>WebServer.Endpoints.HealthCheck.LicenseCheck</code>	boolean	true	Set to false to disable the license check, true to enable it
<code>WebServer.Endpoints.HealthCheck.Pool.Document</code>	boolean	true	Set to true to exercise the document kernel pool, false to disable it
<code>WebServer.Endpoints.HealthCheck.Pool.Compute</code>	boolean	true	Set to true to exercise the compute kernel pool, false to disable it
<code>WebServer.Endpoints.HealthCheck.Pool.Fallback</code>	boolean	true	Set to true to exercise the fallback kernel pool, false to disable it
<code>WebServer.Endpoints.HealthCheck.KernelTimeout</code>	positive integers	10	The amount of time (in seconds) the check will wait for a kernel to return the results of the test command
<code>WebServer.Endpoints.HealthCheck.QueueTimeout</code>	positive integers	10	The amount of time (in seconds) the check will wait for a kernel to be allocated from a pool

Monitoring

The monitoring endpoint is `/monitoring/`. When an HTTP GET accesses this endpoint, a snapshot of the internal state of MapleNet as a string of JSON is returned. The information displayed can be divided into two types, static values and dynamic values. The static values are values defined at MapleNet start up time, for example configuration values and version information. Dynamic values are values that change as clients connect to MapleNet, for example connected clients and open documents. If you want to view the monitoring data in a web browser, plugins are available for pretty printing JSON. This makes the monitoring output more human readable.

Value	Definition
limiter	The limiter describes the number of running Maple engines. A running Maple engine corresponds to the restrictions imposed by the license. A waitingEngine is an engine that can't run because the maximum number of running engines has been reached.
engineManager	The engineManager provides a detailed breakdown of the Maple engines in use by MapleNet. Document engines are engines connections to open documents. Compute engines are used for the compute endpoint. As compute engines are pooled and reused, there is list of pooled compute engines.
documentManager	The documentManager section describes the documents currently opened by clients. Each open document lists the following fields: id a unique id assigned to that copy of the open document, the name of the document, the working directory of the document and the source of the document. The working directory is where the content created for displaying the document is kept.
clients	The clients section describes the document clients currently connected to MapleNet Server. Each client lists the IP address from which they are connected and the id of the document that they have opened.
helpDatabases	The helpDatabases section describes the help database found for use with the help endpoints.
Version	The Version section describes the versions of the various pieces used by MapleNet. This include the MapleNet and Maple build dates, release ids and build ids. These values are useful when reporting bugs or contacting Maplesoft Support.
license	The license section describes the license being used.
Start Up Configuration	The Start Up Configuration section describes the values applied by the MapleNet configuration. This combines the options set with configuration variables and default values.

Logging	The Logging section describes the current logging settings, the level and whether AutoFlush or Synchronous options are enabled.
---------	---

Metrics over Prometheus

Metric Group: Web Endpoint Handling

Metric	Metric Type	Domain	Description
request_latency_seconds	Histogram	Non-negative double	<p>A histogram of HTTP request handling latencies. Each datapoint is given two labels: the HTTP request method, and the handler.</p> <p>The HTTP methods are:</p> <ul style="list-style-type: none"> • get • post • put • delete • head • options • patch

The handlers are:

Handler Name	Expected HTTP Method	Purpose
worksheet	get	The handler responds to requests to *.mw and *.maple
html_file	get	Responds to *.html. Performs substitutions in html files, namely <code>_\${MAPLE_CLOUD_CDN}</code> to the maple cloud cdn value provide in the docker configuration.
soap	get	Responds to SOAP requests at <code>/services/MapleService</code>
mcs	post	Responds to <code>/mnserver/mcs</code> protobuf requests.
compute	post	Responds to <code>/mnserver/compute</code>
attachment	get	Responds to <code>/attachment/</code>
version	get	Responds to <code>/maplenet/mnstatus/version.jsp</code>
upload	post	Responds to <code>/upload</code>
monitoring	get, post	Responds to <code>/monitoring/</code>
healthcheck	get	Responds to <code>/healthcheck/</code>

Metric Group: Webserver Monitoring

Metric	Metric Type	Domain	Description
active_connections	Gauge	Non-negative integer	The current number of connections

max_active_connections	Counter	Non-negative, monotonically increasing integer	High watermark for the maximum number of simultaneous connections.
connections_total	Counter	Non-negative, monotonically increasing integer	The total number of connections that the webserver has handled
requests_total	Counter	Non-negative, monotonically increasing integer	The total number of requests that the webserver has handled.
data_received_bytes_total	Counter	Non-negative, increasing integer	The total number of bytes the webserver has received.
data_sent_bytes_total	Counter	Non-negative, increasing integer	The total number of bytes the webserver has sent

Metric Group: Prometheus Webserver Monitoring

Metric	Metric Type	Domain	Description
exposer_transferred_bytes_total	Counter	Non-negative, increasing integer	The number of bytes the prometheus webserver has transmitted on the /metrics page
exposer_scrapes_total	Counter	Non-negative, monotonically increasing integer	The number of times the /metrics page has been generated
exposer_request_latencies	Summary	Non-negative float	The amount of time it takes to generate the response to the /metrics page

Metric Group: Kernel Pool Monitoring

Metric	Metric Type	Domain	Description
engines	Gauge	Non-negative integer	The number of engines running. Two labels on this statistic are "pool", which can be "document", "compute", or "fallback". And "state", which can be "idle", or "running". Note: MapleNet does not pool document kernels, therefore there will never be a metric with both pool=document and state=idle.
promised_engines	Gauge	Non-negative integer	Note: This does not distinguish between waiting document, compute, or fallback kernels.

Metric Group: Protobuf Messages Monitoring

Metric	Metric Type	Domain	Description
workbook_handler_latency_seconds	Summary	Non-negative float	Records the amount of time it takes to handle each protobuf message received on the websocket. There is a unique label for each type of protobuf message. The server does not have

			handlers for each message, thus some message types are currently unreported. Some message types are only meant to be sent from the server (for instance, <code>ENGINE_STATUS</code>).
--	--	--	--

The reported messages are:

Message Type	Description
<code>WORKSHEET_RENDER_COMPLETE</code>	Sent by the client when it has fully rendered the page.
<code>UPDATE_IMAGE</code>	Sets the content of an image from a specified file
<code>UPDATE_CONTENTS</code>	Updates the string contents of a model
<code>SET_MODEL</code>	Sets and saves the content for a model
<code>SEND_MODEL_UPDATE</code>	Sends a model update from the server to the client
<code>QUERY_MODEL</code>	Returns the value of a specific component (optionally including subcomponents) on a page
<code>QUERY_CONTENTS</code>	Returns a model's content for a specific model id
<code>OPEN_WORKSHEET</code>	Use to open a worksheet
<code>MODEL_UPDATE</code>	An event fired by the server when a change in the model has happened, or when a client wants to update the state of the model.
<code>GET_ATTACHMENT_URL</code>	Gets the URL for an attachment
<code>GENERATE_PLOT_IMAGE</code>	Generates an image for a plot. For instance, used to generate a thumbnail image of a plot.
<code>EXECUTE_WORKBOOK_COMMAND</code>	Executes a workbook command. A workbook command is a message internal to the MapleNetServer. Workbook handlers can be made of a sequence of workbook commands.
<code>EC_SERVER_EVENT</code>	Encodes plot events (play, pause, stop, etc)
<code>EC_EVENT</code>	Events for embedded components (button clicks, slider changes).
<code>COMPUTE_PLOT</code>	Used during testing
<code>CLICK_BUTTON_GROUP</code>	A button client event

Messages that the server doesn't explicitly handle (but accepts and no-ops):

Message Type	Description
<code>OPEN_FILE</code>	A message used to open a file within a workbook
<code>PING</code>	An application level ping, separate from the websocket-level ping message
<code>CONFIG_OPTIONS</code>	A message the server sends to the client to provide configuration values
<code>ACTIVE_CLIENTS</code>	Used to provide statistics about the open documents of each client
<code>VERSION</code>	A message the server sends to the client to provide version information
<code>ERROR_MESSAGE</code>	A message the server sends to the client so that the client can display an error message generated by the server
<code>DOCUMENT_LOAD_COMPLETE</code>	A message the client sends to the server when a document has finished loading
<code>OPEN_WORKBOOK</code>	The first message in a two step process to open worksheets
<code>ENGINE_STATUS</code>	A message the server sends to the client to indicate when a kernel has started (or stopped) running
<code>WORKSHEET_SAVE_STATE</code>	A message the server sends to the client to indicate information about the saved state of the worksheet

Metric Group: License

Metric	Metric Type	Domain	Description
<code>license_expiry_remaining_seconds</code>	Gauge	Non-negative, monotonically decreasing integer	Reports the amount of time until a license will expire. The label "feature" is used to differentiate different license. If a license is unexpiring, the entry for

			<p>the license is "Nan".</p> <p>Note: We do not report the time remaining as an atomic operation. Each time we calculate the amount of time remaining on a license, we get the current time in milliseconds. Therefore, if two licenses have the same expiry, the output of monitoring will report a slight discrepancy between the amount of time remaining for each license.</p>
--	--	--	--

Metric Group: Kernel

Metric	Metric Type	Domain	Description
kernel_command_seconds	Summary	Non-negative float	Reports the amount of time it takes for an engine to perform a command. All commands are aggregated into the same metric, kernel_command_seconds, unless the command is a bellwether command where it is uniquely identified with a "command" label. A bellwether command is a command that is run on every kernel. Bellwether commands include "_libraryversion();", "kernelopts(toolboxversion);", "kernelopts(version);", and "interface(version);". All of these commands are executed on a kernel every time a kernel is started. The results are used to initialize MapleNetServer values. Because these commands are always executed, variations in these values could indicate a change in the deployment's health or performance.

Bellwether commands:

Command	Description
<code>_libraryversion();</code>	Kernel values needed by MapleNetServer. Executed ever time a new kernel is started.
<code>kernelopts(toolboxversion);</code>	Kernel values needed by MapleNetServer. Executed ever time a new kernel is started.
<code>kernelopts(version);</code>	Kernel values needed by MapleNetServer. Executed ever time a new kernel is started.
<code>interface(version);</code>	Kernel values needed by MapleNetServer. Executed ever time a new kernel is started.
<code>License Check;</code>	The license check performed every time a kernel is started.
<code>2+3;</code>	The command sent to a kernel (in each of the compute, document, and fallback pools—if configured) when <code>/healthcheck/</code> is queried.

Note: bellwether commands are lazily added to the list of kernel_command_seconds and are not added to the list of kernel_command_seconds until the command is first executed. For instance `kernel_command_seconds{command="2+3"}` will not appear in the list until the first time the health check is queried.

5 Example Configurations

This section contains example configurations for typical MapleNet deployments

The following variables are used in this document, and should be replaced with the correct values:

LICENSEFILE: The location of the MapleNet license file (on the Docker host)

HOSTPORT: The port on the host machine on which MapleNet should accept connections

IMAGETAG: The tag of the Docker image created by the installer

CONTENTDIR: The directory containing Maple content for hosting by MapleNet (on the Docker host)

MAPLEONLINECDNURL: The URL of a Content Delivery Network hosting the MapleNet JavaScript libraries

MATHJAXCDNURL: The URL of a Content Delivery Network hosting the MathJax JavaScript package

Additional documentation for the configuration variables used in these examples is available in the Configuration section of the Administrators Guide. These examples are shown as separate commands, however arguments from one example can, in general, be combined with arguments from other examples.

Note: In the following examples long commands are broken across multiple lines. The `\` character is used to indicate the continuation of the command on the next line. This is supported in many terminals so copying and pasting the entire command should work. If that does not work, duplicating the command as a single line by omitting these characters and joining the argument should also work.

5.1 Basic Document Hosting

These configurations are for customers who want to host Maple documents located within a directory on the Docker host machine.

Mounting as a subdirectory of /webroot

The easiest way to add user content to the container is to simply mount the directory containing the content as a subdirectory of `/webroot`.

```
docker run --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \  
  --mount type=bind,source=$CONTENTDIR,target=/webroot/content \  
  --publish $HOSTPORT:8080 \  
  --rm \  
  maplesoft/maplenet:$IMAGETAG
```

With this configuration, the files in the `$CONTENTDIR` directory are available under

`http://localhost:$HOSTPORT/content`

If you want to be able to navigate the directory structure via the web browser you can enable directory listings using the `MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING` variable.

With this configuration the default locations of MapleNet's libraries are unaffected by the mount. However this does leave the MapleNet landing page and example document on the server. If you want to replace the entire `/webroot` directory, the following configuration will do that.

Mounting on top of /webroot

Replacing `/webroot` completely will hide the JavaScript libraries required for document rendering in MapleNet. Therefore you will need to either use a Content Delivery Network (see next configuration) or copy those libraries into your content directory so they continue to be available when `/webroot` is hidden. To copy the libraries from the Docker image, we first need to start the image. This is only to access the files, so a simple `docker run` command is sufficient.

```
docker create --name copy_container \
  --rm maplesoft/maplenet:$IMAGETAG
```

We use the `--name` option to give the container a easy to remember name. We can now copy the directory containing the MapleNet libraries to the directory of content we want to mount on top of `/webroot`.

```
docker cp -a copy_container:/webroot/mapleonline $CONTENTDIR
docker cp -a copy_container:/webroot/MathJax $CONTENTDIR
```

Now stop this container

```
docker stop copy_container
```

There should now be directories named `mapleonline` and `MathJax` within `$CONTENTDIR` containing the JavaScript libraries from the Docker container.

Now we can start the Docker container with `$CONTENTDIR` replacing `/webroot`

```
docker run --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

With this configuration, the `$CONTENTDIR` directory is the root of the files served by MapleNet.

Using a Content Delivery Network for JavaScript libraries

If you are able to use a Content Delivery Network (CDN) to host MapleNet's JavaScript libraries this can simplify the process of replacing `/webroot` as the MapleNet content is no longer require to exist within the Docker container. However to place the content on a CDN, it still needs to be extracted from the Docker image as described above. To use a CDN, the following command should be used

```
docker run --env MAPLENET_WEBSERVER_MAPLECLOUDCDN=$MAPLEONLINECDNURL \
  --env MAPLENET_WEBCLIENT_CONFIGURATION="MathJaxCDN=$MATHJAXCDNRURL" \
  --publish $HOSTPORT:8080 \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
```

```
--rm \
maplesoft/maplenet:$IMAGETAG
```

Logging Configuration

The following example configures the json-file logger (the docker default) to perform log rotation with three log files each with a maximum size of 10 Mb. Thus if the current log file reaches 10 Mb and there are already three log files, the oldest is deleted and a new log file is created.

```
docker run --log-opt max-size=10m \
  --log-opt max-file=3 \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

The MapleNet container can also be configured to pass its logs to standard logging facilities, for example

```
docker run --log-driver syslog \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

For a complete list of supported logging facilities, see the docker log driver documentation:

<https://docs.docker.com/config/containers/logging/configure/>

5.2 Basic Compute Hosting

This example configuration is for MapleNet's compute API. The primary concern for the compute API is usually resource limits. The following command starts MapleNet with restricted compute limits of 5 seconds of compute time and 500 MiB of memory.

```
docker run --env MAPLENET_POOL_COMPUTATIONTIMELIMIT=5 \
  --env MAPLENET_COMPUTEENGINE_DATALIMIT=500 \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

Cross-Origin Resource Sharing (CORS)

Cross-Origin Resource Sharing is a mechanism for allowing web applications running on one domain to access web services running on another. Normally web browsers do not allow applications to access services running on different domain. CORS allows the service to state if a domain is allowed to make requests to the server. This may be important for the compute service if users have written web applications hosted on other domains and want access the compute service. By default MapleNet is configured to not allow requests from different domains.

The following configuration allow requests from any domain

```
docker run --env MAPLENET_WEBSERVER_CORS_ALLOWORIGIN="*" \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

If you have a list of domains you are willing to accept requests from you can use a comma separated list of domain names

```
docker run --env MAPLENET_WEBSERVER_CORS_ALLOWORIGIN="domain1.com,domain2.com,domain3.com" \
  --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

5.3 Adding Maple Libraries and Help Databases

Users can add Maple libraries and help databases to MapleNet. Adding Maple libraries allows hosted documents and compute requests to access the Maple functionality in those libraries. Adding help databases allows MapleNet to host Maple help pages for display in browsers. In this example we will simply add the user libraries and help databases to the Maple library directory. For this example, we'll use `$MAPLELIBRARYDIR` to represent the path to a Maple library (.mla) `$MAPLELIBRARY` and `$MAPLEHELPPDIR` to represent a the path to a Maple help database (.help) `$MAPLEHELP`.

```
docker run --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --mount type=bind,source=$MAPLELIBRARYDIR/$MAPLELIBRARY,target=/maple/lib/$MAPLELIBRARY \
  --mount type=bind,source=$MAPLEHELPPDIR/$MAPLEHELP,target=/maple/lib/$MAPLEHELP \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

Multiple libraries and help database can be added by having multiple mount commands.

Care must be taken to not override the default Maple libraries (maple.mla, update.mla,MathematicalFunctions.mla or MTM.mla) as this would remove Maple (and MapleNet) functionality. If the name of your library conflicts with an existing Maple library, you can simply mount it with a different name.

```
docker run --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
  --mount type=bind,source=$CONTENTDIR,target=/webroot \
  --mount type=bind,source=$MAPLELIBRARYDIR/maple.mla,target=/maple/lib/mymaple.mla \
  --publish $HOSTPORT:8080 \
  --rm \
  maplesoft/maplenet:$IMAGETAG
```

Changing the URL for the Help Database

If you are hosting a help database, you can change the value of URL that MapleNet uses for help by using the `WebClient.HelpUrl` command parameter.

For example, to instruct MapleNet to use "http://exampledatabase.com/help" as the help database URL:

```
docker run --mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly
--publish $HOSTPORT:8080 maplesoft/maplenet:$IMAGETAG
--WebClient.HelpUrl "http://exampledatabase.com/help"
```

(5.1)

5.4 Enabling the Upload Page

MapleNet includes an upload page that allows users to upload Maple documents to MapleNet from their web browsers. To enable this feature the `MAPLENET_WEBSERVER_ENDPOINTS_UPLOAD` variable must be set. In addition, the upload page displays the contents of the upload directory if `MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING` is set.

```
docker run --env MAPLENET_WEBSERVER_ENDPOINTS_UPLOAD=true \
--env MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING=true \
--mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
--mount type=bind,source=$CONTENTDIR,target=/webroot/content \
--publish $HOSTPORT:8080 \
--rm \
maplesoft/maplenet:$IMAGETAG
```

With these variables set, the upload page

```
http://$HOSTNAME/mapleonline/upload/upload.html
```

will be fully functional.

By default the upload directory lives within the docker container, thus when the container is restarted any uploads are lost. To have the uploaded content persist between MapleNet restarts, mount a host directory on top of the upload directory. With this, the uploads are saved to the host directory. If `/webroot` is replaced with a host directory (as described above), uploads will be stored into the host directory. If that is not the case, the following command mounts the `$UPLOADDIR` from the host machine on top of the MapleNet upload directory.

```
docker run --env MAPLENET_WEBSERVER_ENDPOINTS_UPLOAD=true \
--env MAPLENET_WEBSERVER_ENABLEDIRECTORYLISTING=true \
--mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
--mount type=bind,source=$CONTENTDIR,target=/webroot/content \
--mount type=bind,source=$UPLOADDIR,target=/webroot/worksheet/upload \
--publish $HOSTPORT:8080 \
--rm \
maplesoft/maplenet:$IMAGETAG
```

5.5 Security Options

The following options implement the suggested configuration in the Security section of the Administrators Guide. It also mounts `$CONTENTDIR` on top of `/webroot` as described above.

```
docker run --env MAPLENET_ENDPOINTS_COMPUTE=false \
--env MAPLENET_ENDPOINTS_HELP=false \
--env MAPLENET_DOCUMENTENGINE_CPULIMIT=120 \
--env MAPLENET_DOCUMENTENGINE_DATA LIMIT=2048 \
--mount type=bind,source=$LICENSEFILE,target=/maple/license/license.dat,readonly \
--mount type=bind,source=$CONTENTDIR,target=/webroot \
--publish $HOSTPORT:8080 \
```

```
--rm \  
maplesoft/maplenet:$IMAGETAG
```

5.6 Troubleshooting

Docker not starting

Error: Bind for \$HOSTPORT failed: port is already allocated

The port you specified for MapleNet to listen on is already in use. This could be caused by an existing MapleNet instance using the same port. Running

```
docker ps
```

will show all the running Docker containers as well as the port they are using. You can use `docker stop` to stop a running container or select a different port for MapleNet.

MapleNet is not starting

Error: The license file, /maple/license/license.dat, does not exist

This indicates that MapleNet was unable to locate a valid license. Make sure you completed the installation step to obtain a valid license and that it was correctly mounted into the Docker container.

Error: Unable to create compute cache directory

If you are mounting on top of `/webroot`, MapleNet needs to be able to create directories in the mounted directory. The permissions on the `$CONTENTDIR` may be preventing MapleNet from doing so.

Performances Issues

Error: Users seeing "Time out" errors when accessing MapleNet

When users see time out errors when connecting to MapleNet, this usually indicates that MapleNet is overloaded. There are a few configuration options that may be able to solve these issues.

`MAPLENET_WEBSERVER_NUMTHREADS`: The MapleNet web server has a limited number of threads to handle incoming connections. If you are handling a large number of incoming connections you may need to increase this value. Be aware that increasing the number of web server threads also increases the amount of memory MapleNet will use.

`MAPLENET_POOL_MAXENGINES`: MapleNet maintains a pool of Maple engines. If there are a large number of open documents, it is possible to reach this limit. Increasing this limit will allow more users to have open documents on MapleNet. Each running Maple engine requires memory, so this will also lead to higher memory usage. This variable does not effect the maximum number of **running** engines, simply the maximum number of open engines.

`MAPLENET_POOL_QUEUELIMIT`: MapleNet has a limit on the number of engines that can run at the same time (limited by the MapleNet license). When MapleNet runs a command it may need to wait if the maximum number of engines are already running. This variable determines how long MapleNet should wait for an available engine before aborting.

`MAPLENET_WEBSERVER_REQUESTTIMEOUTMS`: This variable limits how long MapleNet keeps a connection open when it stops receiving messages from a client. The MapleNet client sends regular messages to keep the connection alive and these are normally sufficient. However if users have low speed or unreliable connections, this timeout may be exceeded, and the connection closed.

MapleNet memory usage

MapleNet allows multiple users to run commands in Maple on a single server. This can use a lot of memory, potentially making the host machine unstable. If you have problems with excessive memory usage, you can try adjusting the following variables.

`MAPLENET_POOL_MAXENGINES`: Reduce the maximum number of open Maple engines, with the trade off of allowing fewer users to access MapleNet.

`MAPLENET_COMPUTEENGINE_DATALIMIT` and `MAPLENET_DOCUMENTENGINE_DATALIMIT`: These variables limit the amount of memory a single compute or document engine can use. Setting these limits will stop individual connections from using a large amount of memory, with the trade off that large computations may not be able to finish.

`MAPLENET_ENGINE_JAVADATALIMIT`: If you see mjava processes consuming large amounts of memory, adjusting this variable may help. In some circumstances (machines with a large amount of memory) the java virtual machine may use a large amount of memory instead of collection more quickly. This variable forces java to work within a smaller memory footprint.

Increase the number of allowed running engines

If the none of the suggestions above help, and you are seeing high load on the machine, then you many need to increase the number of licensed running engines. Before doing this, verify that during peak load times, you are seeing one running engine for each allowed running engine in your license. The easiest way to do this is to look at the MapleNet monitoring page. In the limiter section you should see three values, `maxRunningEngines`, `runningEngines` and

`waitingEngines`. If `waitingEngines` is greater than 0, then MapleNet is running at or beyond its optimal capacity. You may need to increase your number of licensed engines to allow more engines to run in parallel. This only makes sense if you also have available CPU resources. MapleNet is designed to run with one core per running engine. Running MapleNet with more allowed running engines than CPU cores is not suggested, and will not increase performance.

6 Copyright

6.1 Client Side Software Copyright Statements

error_prone_annotations

<http://www.apache.org/licenses/LICENSE-2.0>

j2objc-annotations 1.3

Copyright © 2015 Google, Inc.

<http://www.apache.org/licenses/LICENSE-2.0>

guava 23.0

Copyright © 2017 Google, Inc

<http://www.apache.org/licenses/LICENSE-2.0>

guava-gwt 23.0

Copyright © 2017 Google, Inc.

<http://www.apache.org/licenses/LICENSE-2.0>

gwtquery 1.5 beta 1

Copyright © 2017 Google, Inc

<http://www.apache.org/licenses/LICENSE-2.0>

gwtexporter 2.5.0

Copyright © 2007 Timepedia.org

<http://www.apache.org/licenses/LICENSE-2.0>

eventbinder 1.10

Copyright © 2014 Google, Inc.

<http://www.apache.org/licenses/LICENSE-2.0>

akjava

Copyright © 2011- 2013 Aki Miyazaki

<http://www.apache.org/licenses/LICENSE-2.0>

gwt-log 3.3.2

Copyright © 2014 Google, Inc.

<http://www.apache.org/licenses/LICENSE-2.0>

GWT 2.8.1

Copyright © Google, Inc.

<http://www.apache.org/licenses/LICENSE-2.0>

6.2 Server Side Software Copyright Statements

Maple Licensed Code

Maple/MapleNet has licensed code from the following sources:

Star Division GmbH

- Portions Copyright © 1991 - 1994 by Star Division GmbH.

Mathematics Dictionary

- The mathematics dictionary utilized both in whole and in parts within the Help system of Maple is utilized with the permission of MathResources Inc., and the authors of the database Borwein, Dr. Jonathan and Borowski, Mr. Ephraim (1997), The MathResource: Interactive Math Dictionary. Nova Scotia: MathResources Inc. (www.mathresources.com).

FLEXIm

- FLEXIm Copyright © 1994, 2004 by Macrovision Corporation.

Intel

- Intel® MKL Copyright © 1999, 2000-2008 Intel Corporation. All rights reserved.
- Intel® IPP Copyright © 2012 Intel Corporation. All rights reserved.
- Intel® RunTime Copyright © 2012 Intel Corporation. All rights reserved.

Dr. Piet Jonas

- WMFWriter

<http://piet.jonas.com/WMFWriter/WMFWriter.html>

Microsoft

- MSVC Redistributable

Microsoft Software License Terms MSVC 2013

Microsoft Software License Terms MSVC 2015

NICONET

- NICONET

The Maple routines LinearAlgebra[CARE] and LinearAlgebra[DARE] are based on the SLICOT library. All rights, title and interest in and to SLICOT is, and shall at all times remain, the sole and exclusive property of NICONET as the developers of the software library. Maplesoft shall have all right, title and interest in and to any modifications, error corrections, derivatives, or enhancements made from or to SLICOT by Maplesoft.

<http://www.niconet-ev.info/en/>

<http://www.slicot.org/>

TeamDev

- JNIWrapper

<https://www.teamdev.com/jniwrapper-licence-agreement>

Open Source

Abseil Python Common Libraries

Abseil Python Common Libraries (absl-py) - © 2018 The Abseil Authors

<https://github.com/abseil/abseil-py>

Apache License Version 2.0

Adaptive Precision Floating-Point Arithmetic and Fast Robust Predicates for Computational Geometry

This code is in the [public domain](#)

<https://www.cs.cmu.edu/%7Equake/robust.html>

Apache Batik

- Apache Batik 1.10 - Copyright © 2002-2018 The Apache Software Foundation.

<http://xmlgraphics.apache.org/batik/>

Apache License Version 2.0

Apache Commons Codec

- Apache Commons Codec 1.8 - Copyright © 2002-2013 The Apache Software Foundation.

<http://commons.apache.org/proper/commons-codec/archives/1.8/index.html>

Apache License Version 2.0

Apache Commons IO

- Apache Commons IO 2.4 - Copyright © 2002-2014 The Apache Software Foundation.

<http://commons.apache.org/proper/commons-io/>

Apache License Version 2.0

Apache FOP

- Apache FOP - Copyright © 1999-2010 The Apache Software Foundation

<http://xmlgraphics.apache.org/fop/>

Apache License Version 2.0

Apache log4j

- Apache log4j 1.2.3 - Copyright © 1999-2012 The Apache Software Foundation

<http://logging.apache.org/log4j/1.2/>

Apache License Version 2.0

Apache POI

- Apache POI 3.17 - Copyright © 2002-2010 The Apache Software Foundation.

<http://poi.apache.org/>

Apache License Version 2.0

Apache Xerces2 Java

- Apache Xerces2 Java Parser 2.3.0 - Copyright © 1999-2003 The Apache Software Foundation.

<http://xerces.apache.org/xerces2-j>

Apache License Version 2.0

Apache Xalan-Java

- Apache Xalan-Java - Copyright © 1999-2014 The Apache Software Foundation. All rights reserved.

<https://xalan.apache.org/>

Apache License Version 2.0

Apache XMLBeans

- Apache XMLBeans 2.3.0 - Copyright © 2004 The Apache Software Foundation. All rights reserved.

<http://xmlbeans.apache.org/>

XMLBeans NOTICE

Apache License Version 2.0

arb

- C library for arbitrary-precision interval arithmetic.

Copyright © 2012-2018, Fredrik Johansson

The **arb** library is distributed under the terms of the GNU Lesser General Public License Version 2.1. In accordance with this license, we are making the version of the arb source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>.

GNU Lesser General Public License

astor -- AST observe/rewrite

Copyright © 2012, Patrick Maupin

Copyright © 2013, Berker Peksag

Copyright © 2008, Armin Ronacher

<https://github.com/berkerpeksag/astor>

BSD License (3-Clause)

ATLAS

- ATLAS Automatically Tuned Linear Algebra Software Copyright © 1998-2008 R. Clint Whaley.

<http://math-atlas.sourceforge.net>

ATLAS License Agreement

Beautiful Soup

- Copyright © 2004-2018 Leonard Richardson. Distributed under the terms of the MIT License.

Beautiful Soup incorporates code from the html5lib library, which is also made available under the MIT license. Copyright © 2006-2013 James Graham and other contributors.

BLAD

- BLAD, BMI

The Maple package DifferentialAlgebra uses the **BLAD** and **BMI** libraries. These libraries are free and are protected under the **GNU Lesser General Public License Version 2.1**.

In accordance with this license, we are making the versions of the **BLAD** and **BMI** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file for each is included (see "COPYING.LIB").

GNU Lesser General Public License

bleach

- Copyright © 2014-2016, Mozilla Foundation. Distributed under the terms of the Apache License Version 2.0.

Boost

- Boost - Copyright © 1999-2015 Boost contributors

<http://www.boost.org/>

Boost License Agreement

Civetweb

Copyright © 2013-2018 The CivetWeb developers

<https://github.com/civetweb/civetweb>

CLAPACK

- CLAPACK

Maple uses portions of the CLAPACK library. For more information, see **LAPACK Users' Guide**, Third Edition by Anderson, E.; Bai, Z.; Bischof, C.; Blackford, S.; Demmel, J.; Dongarra, J.; Du Croz, J.; Greenbaum, A.; Hammarling, S.; McKenney, A.; and Sorensen, D. or visit:

<http://www.netlib.org/lapack/lug/>

<http://www.netlib.org/clapack/>

CLAPACK License Agreement

<http://www.netlib.org/lapack/>

LAPACK License

ControlsFX

- ControlsFX - Copyright © 2013, 2014

<http://fxexperience.com/controlsfx/>

ControlsFX License

CoolProp

- CoolProp

The Maple package ThermophysicalData uses the CoolProp library. For more information, see <http://www.coolprop.org/> or the citation below.

The license for the CoolProp library is available on the License-CoolProp help page.

Bell, Ian H.; Wronski, Jorrit; Quoilin, Sylvain; and Lemort, Vincent. **Pure and Pseudo-pure Fluid Thermophysical Property Evaluation and the Open-Source Thermophysical Property Library CoolProp**. Industrial & Engineering Chemistry Research, Vol. **53** No. 6 (2014), pp. 2498--2508; <http://www.coolprop.org/>.

Cuba

- Cuba

Maple uses the **Cuba** library, developed by Thomas Hahn and distributed via <http://www.feynarts.de/cuba/>. It is distributed under the terms of the **GNU Lesser General Public License Version 3**. In accordance with this license, we are making the version of the **Cuba** source code that Maple uses available for download via <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included in the archive available there (see "COPYING").

GNU Lesser General Public License version 3

CUDA

- CUDA

The Maple package CUDA uses the CUDA® library from NVIDIA®.

<https://developer.nvidia.com/cuda-toolkit>

[NVIDIA License](#)

cURL

- cURL 7.62.0 Copyright 1996 - 2018 David Stenberg and others (see [THANKS](#) page)

<https://curl.haxx.se/>

cURL License

DocBook XSL Stylesheets

Copyright © 1999-2007 Norman Walsh

Copyright © 2003 Jiří Kosek

Copyright © 2004-2007 Steve Ball

Copyright © 2005-2009 The DocBook Project

DocBook XSL Stylesheets License Agreement

<http://docbook.sourceforge.net/>

dom4j

- dom4j Copyright © 2001 - 2016 by MetaStuff, Ltd. and DOM4J contributors. All Rights Reserved.

dom4j Copyright and License Agreement

enum34

- Copyright © 2013, Ethan Furman. Distributed under the terms of the BSD License (3-Clause).

f2c

- f2c Copyright © 1990 - 1997 by AT&T, Lucent Technologies and Bellcore.

f2c Copyright and License Agreement

FLINT

- FLINT: Fast Library for Number Theory

FLINT is a C library for doing number theory, maintained by William Hart.

The **FLINT** library is distributed under the terms of the GNU Lesser General Public License Version 2.1. In accordance with this license, we are making the version of the FLINT source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>.

GNU Lesser General Public License

FreeHEP

- The **FreeHEP** Java library is distributed under the terms of the **GNU Lesser General Public License Version 2.1**. In accordance with this license, we are making the version of the **FreeHEP** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/FreeHEP.html>. A copy of the license file is included (see "COPYING.LIB").

GNU Lesser General Public License

gast

- Copyright serge-sans-paille. Distributed under the terms of the BSD License (3-Clause).

<https://pypi.org/project/gast/>

GCC

- The GCC Runtime Libraries - Copyright © 2009 Free Software Foundation, Inc.

The GCC Runtime Libraries source code is distributed under the **GNU General Public License version 3** with the additional permission of the **GCC Runtime Library Exception**.

In accordance with this license, we are making the version of the **GCC** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included (see "COPYING.RUNTIME").

GNU Lesser General Public License version 3

GCC Runtime Library Exception

<http://gcc.gnu.org>

GeoNames

- All works from GeoNames are licensed under the Creative Commons Attribution 3.0 License.

<http://www.geonames.org/>

CC BY 3.0

GL2PS C library

- Copyright © 2003 Christophe Geuzaine

In accordance with this license, we are making the version of the **GL2PS** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included (see "COPYING.GL2PS").

GL2PS License Agreement

GMP

- **GMP 5.1.1** Copyright © 1996 - 2013.

The **GMP** library is distributed under the terms of the **GNU Lesser General Public License Version 3**. In accordance with this license, we are making the version of the **GMP** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/GMP.html>. A copy of the license file is included (see "COPYING.LIB").

GNU Lesser General Public License version 3

google

- Google search from Python.

Copyright © 2018 Mario Vilas. Distributed under the terms of the BSD License (3-Clause).

<https://breakingcode.wordpress.com/2010/06/29/google-search-python/>

grpcio

- Copyright © 2015 - 2018 the gRPC authors.

Distributed under the terms of the Apache License Version 2.0.

<https://pypi.org/project/grpcio/>

Henry Spencer

- Regular expression code. Copyright © 1986, 1993, 1995 by University of Toronto. Written by Henry Spencer.

Henry Spencer Permission Statement

html5lib

- Copyright © 2006-2013 James Graham and other contributors.

Distributed under the terms of the MIT License.

<https://pypi.python.org/pypi/html5lib>

ICU

- International Components for Unicode

Copyright © 1995-2015 International Business Machines Corporation and others

ICU License

<http://site.icu-project.org/>

Info-Zip

- Info-Zip - Copyright © 1990-2009 Info-ZIP. All rights reserved.

<http://www.info-zip.org/>

Info-Zip License

iText

- iText Library - Copyright © 1999-2009 by Bruno Lowagie and Paulo Soares. All rights reserved.

The **iText** library is distributed under the terms of the GNU Lesser General Public License Version 2.1. In accordance with this license, we are making the version of the iText source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included (see "COPYING.LIB").

GNU Lesser General Public License

<http://www.itextpdf.com/>

Java

- Java is a registered trademark of Oracle and/or its affiliates.

Oracle Binary Code License Agreement for the Java SE Platform Products and JavaFX

JavaMail

JavaMail uses several licenses:

- Most of the JavaMail source code is licensed under the CDDL license and the GPLv2 with Classpath Exception license; see the license information at the top of each source file.
- The source code for the demo programs is licensed under the BSD license; again, the license is in each source file.
- The binary jar files published to the Maven repository are licensed under the same CDDL and GPLv2+CE licenses as the corresponding source code; see the file META-INF/LICENSE.txt in each jar file.
- The JavaMail API specification is licensed under the standard JCP Specification License.

You'll find the text of the CDDL and GPLv2+CE licenses in the workspace in the file mail/src/main/resources/META-INF/LICENSE.txt. The specification license is in the workspace at mail/src/main/java/doc-files/speclicense.html. Don't let the presence of these license files in the workspace confuse you into thinking that they apply to all files in the workspace.

In accordance with the CDDL, we are making the version of the **JavaMail** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>.

The BSD License

JavaMail CDDL and GPLv2 with Classpath Exception

JCP Specification License

JOGL

- JOGL (Java Binding for the OpenGL) is distributed under the terms of the **JOGL License**.

JOGL License

<http://jogamp.org/jogl/www/>

- This software is based in part on the work of the Independent JPEG Group.

jsmn

- JSON parser - <http://zserge.com/jsmn.html>

Copyright © 2010 Serge A. Zaitsev. Distributed under the terms of the MIT License.

jsoup: Java HTML Parser

jsoup HTML parser copyright © 2009-2016 Jonathan Hedley

The jsoup code-base (include source and compiled packages) are distributed under the open source MIT License.

<https://jsoup.org/>

JUnit

- JUnit unit testing framework - <http://www.junit.org/>

Distributed under the terms of the Eclipse Public License - v 1.0.

<http://www.junit.org/>

latex2mathml

- Copyright © 2016-2019 Ronie Martinez. Distributed under the terms of the MIT License.

<https://pypi.org/project/latex2mathml/>

L2FProd Common Components

L2FProd 7.3 - Copyright © 2004-2007 L2FProd.com

Apache License Version 1.1

<https://github.com/l2fprod/l2fprod-common>

json-simple

JSON.simple - A simple Java toolkit for JSON

Apache License Version 2.0

<https://code.google.com/archive/p/json-simple/>

Libexslt

- Libexslt - Copyright © 2001-2002 Thomas Broyer, Charlie Bozeman and Daniel Veillard. All Rights Reserved.

Libexslt License Agreement

<http://xmlsoft.org/XSLT/EXSLT/index.html>

LibJPEG

- Copyright © 1991-1998, Thomas G. Lane.

LibJPEG License Agreement

<http://libjpeg.sourceforge.net/>

<http://www.ijg.org/>

libpng

- libpng version 1.6.35 - July 15, 2018

Copyright © 1998-2018 Glenn Randers-Pehrson

(Version 0.96 Copyright © 1996, 1997 Andreas Dilger)

(Version 0.88 Copyright © 1995, 1996 Guy Eric Schalnat, Group 42, Inc.)

libpng License Agreement

<http://www.libpng.org/pub/png/libpng.html>

LibTIFF

- Copyright © 1988-1997 Sam Leffler and Copyright © 1991-1997 Silicon Graphics, Inc.

LibTIFF License Agreement

<http://www.libtiff.org/>

Libxml2

- Copyright © 1998-2012 Daniel Veillard. All Rights Reserved.

Libxml2 License Agreement

<http://xmlsoft.org/>

Libxslt

- Libxslt - Copyright © 2001-2002 Daniel Veillard. All Rights Reserved.

Libxslt License Agreement

<http://xmlsoft.org/XSLT/>

LibYAML

- LibYAML - YAML 0.2.1 parser - <http://pyyaml.org/wiki/LibYAML>

Copyright © 2017-2018 Ingy döt Net © 2006-2016 Kirill Simonov. Distributed under the terms of the MIT License.

LLVM

- LLVM - Copyright © 2003-2013 University of Illinois at Urbana-Champaign.

Clang - Copyright © 2007-2013 University of Illinois at Urbana-Champaign.

LLVM and Clang are distributed under the LLVM Release License.

LLVM Release License

<http://llvm.org>

<http://clang.llvm.org>

MapleSAT

- MapleSAT - An efficient SAT solver based on MiniSat

Copyright © 2016, Jia Hui Liang, Vijay Ganesh

Distributed under the terms of the MIT License.

<https://sites.google.com/a/gsd.uwaterloo.ca/maplesat/>

Markdown

Copyright 2007 - 2008 The Python Markdown Project (v. 1.7 and later)

Copyright 2004, 2005, 2006 Yuri Takhteyev (v. 0.2-1.6b)

Copyright 2004 Manfred Stienstra (the original version)

Distributed under the terms of the BSD License (3-Clause).

Mesa

- Mesa 7.2 - Copyright © 1999 - 2007 by Brian Paul

Copyright © 1994 - 1999 The XFree86 Project, Inc. All rights reserved.

Mesa Copyright and License Agreement

<http://www.mesa3d.org/>

miGIF Compression

- mouse and ivo's GIF-compatible compression

-run length encoding compression routines-

Copyright © 1998 Intuit Inc.

miGIF Permission Statement

MiniSat

- MiniSat is a minimalistic, open-source SAT solver - <http://minisat.se/>

Copyright © 2003-2006, Niklas Eén, Niklas Sörensson

Copyright © 2007-2010, Niklas Sörensson

Distributed under the terms of the MIT License.

Minizip

- Minizip - Copyright © 1998-2010 Gilles Vollant

Version 1.2.11

Minizip: zip.h Copyright and License Agreement

Minizip: unzip.h Copyright and License Agreement

<http://www.winimage.com/zLibDll/minizip.html>

MorphAdorner

- MorphAdorner

Copyright © 2006-2009 by Northwestern University. All rights reserved.

<http://morphadorner.northwestern.edu/morphadorner/>

MorphAdorner License Agreement

MPFR

- The **MPFR** library is distributed under the terms of the **GNU Lesser General Public License Version 2.1**. In accordance with this license, we are making the version of the **MPFR** source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included (see "COPYING.LIB").

GNU Lesser General Public License

<http://www.mpfr.org/>

Nauty

- Nauty and Traces version 2.6r10, released November 25, 2017.

Nauty and Traces are programs for computing automorphism groups of graphs and digraphs. They can also produce a canonical label.

See Nauty Copyright and License Statement for details on copyright and licensing.

<http://pallini.di.uniroma1.it/>

NumPy

- Copyright © 2005-2017, NumPy Developers.

Distributed under the terms of the BSD License (3-Clause).

Open Watcom

- **Open Watcom** is distributed under the terms of the **Sybase Open Watcom Public License**.

Sybase Open Watcom Public License

Part Of Speech Database

- Part Of Speech Database (<http://wordlist.sourceforge.net/pos-readme>), compiled by Kevin Atkinson (kevin@users.sourceforge.net).

The part-of-speech.txt file contains is a combination of "Moby™ Part-of-Speech II" and the WordNet database.

Part of Speech Database Copyright and License

pip

- Copyright © 2008 - 2018, the pip developers.

Distributed under the terms of the MIT License.

<https://pypi.org/project/pip/>

Protocol Buffers

- Protocol Buffers - Google data interchange format

Copyright 2008 - 2018, Google Inc. All rights reserved.

Protocol Buffers License Agreement

<https://developers.google.com/protocol-buffers/>

Pthreads-win32

The **pthread-win32** software is distributed under the terms of the GNU Lesser General Public License Version 2.1. In accordance with this license, we are making the version of the pthread-win32 source code that Maple uses available for download at <http://www.maplesoft.com/support/downloads/source>. A copy of the license file is included (see "COPYING.LIB").

GNU Lesser General Public License

Python

- Python

Copyright © 2001-2017 Python Software Foundation; All Rights Reserved

<http://www.python.org/>

Python License

QuantLib

- QuantLib - A free/open-source library for quantitative finance

<http://quantlib.org/>

QuantLib License

Qhull

- Qhull - Copyright © 1993-2015 C.B. Barber and The Geometry Center.

• <http://qhull.org/>

- Qhull License

RSyntaxTextArea and AutoComplete

- RSyntaxTextArea - Copyright © 2012 Robert Futrell. All Rights Reserved.

RSyntaxTextArea Copyright and License Agreement

<http://bobbylight.github.io/RSyntaxTextArea/>

- AutoComplete - Copyright © 2012 Robert Futrell. All Rights Reserved.

AutoComplete Copyright and License Agreement

<https://github.com/bobbylight/autocomplete>

Setuptools

- Copyright © 2016 Jason R Coombs <jaraco@jaraco.com>

Distributed under the terms of the MIT License.

Six

- Copyright © 2010-2017 Benjamin Peterson

Distributed under the terms of the MIT License.

Sliding Layout and Universal Tween Engine

- Sliding Layout - by Aurelien Ribon

<http://github.com/AurelienRibon/sliding-layout>

Apache License Version 2.0

- Universal Tween Engine - by Aurelien Ribon

<http://code.google.com/p/java-universal-tween-engine/>

Apache License Version 2.0

SCOWL

- Spell Checking Oriented Word Lists (SCOWL). (<http://wordlist.sourceforge.net/scowl-readme>)

Revision 7.1 (SVN Revision 161) January 6, 2011 by Kevin Atkinson (kevina@gnu.org)

SCOWL Copyright and License

SQLite

- SQLite

All of the code and documentation in SQLite has been dedicated to the public domain by the authors. All code authors, and representatives of the companies they work for, have signed affidavits dedicating their contributions to the public domain and originals of those signed affidavits are stored in a firesafe at the main offices of Hwaci. Anyone is free to copy, modify, publish, use, compile, sell, or distribute the original SQLite code, either in source code form or as a compiled binary, for any purpose, commercial or non-commercial, and by any means.

<http://www.sqlite.org/>

TensorBoard

- Copyright 2018 The TensorFlow Authors. All rights reserved.

Distributed under the terms of the Apache License Version 2.0.

TensorFlow

- Copyright 2018 The TensorFlow Authors. All rights reserved.

Distributed under the terms of the Apache License Version 2.0.

termcolor

- Copyright 2008 - 2011 Volvox Development Team.

Distributed under the terms of the MIT License.

Thumbnailator - a thumbnail generation library

Copyright © 2008-2015 Chris Kroells

Distributed under the terms of the MIT License.

<https://github.com/coobird/thumbnailator/>

Triangle

Maple includes triangular meshes generated by Triangle.

<https://www.cs.cmu.edu/%7Equake/triangle.html>

UMFPACK, UFconfig, and AMD

- UMFPACK Version 5.0.2 - Copyright © 1995-2006 by Timothy A. Davis. All Rights Reserved. Used by permission.

UFconfig Version 3.5.0 - Copyright © 2006-2009, Timothy A. Davis. All Rights Reserved. Used by permission.

AMD Version 2.2.1 - Copyright © 2009 by Timothy A. Davis, Patrick R. Amestoy, and Iain S. Duff. All Rights Reserved. Used by permission.

The **UMFPACK** library and supporting libraries **UFconfig** and **AMD** are distributed under the terms of the **GNU Lesser General Public License Version 2.1**. In accordance with this license, we are making the modified versions of the **UFconfig**, **AMD** and **UMFPACK** source code that Maple uses available for download at the following links:

<http://www.maplesoft.com/support/downloads/UFconfig-3.5.0.zip>

<http://www.maplesoft.com/support/downloads/AMD.zip> (a copy of the license file is included - see "README.txt")

<http://www.maplesoft.com/support/downloads/UMFPACK.zip> (a copy of the license file is included - see "README.txt")

The original code is available at: <http://faculty.cse.tamu.edu/davis/SuiteSparse/>.

GNU Lesser General Public License

Webencodings

- Copyright © 2012 by Simon Sapin

python-webencodings License

Werkzeug

- Copyright © 2015 by the Werkzeug Team, see [AUTHORS](#) for more details.

Distributed under the terms of the BSD License (3-Clause).

wheel

- "wheel" copyright © 2012-2014 Daniel Holth <dholth@fastmail.fm> and contributors.

Distributed under the terms of the MIT License.

Z3

- Z3 - Copyright © Microsoft Corporation. All rights reserved.

Distributed under the terms of the MIT License.

<https://github.com/Z3Prover/z3/wiki>

zlib

- zlib general purpose compression library

Copyright © 1995-2017 Jean-loup Gailly and Mark Adler

Version 1.2.11, January 15, 2017

zlib license

<http://zlib.net/>

Font Licenses

Bitstream

- DejaVu fonts

DejaVu fonts are copyright © 2003 by Bitstream, Inc. DejaVu changes are in public domain. Explanation of copyright is on [Gnome page on Bitstream Vera fonts](#). Glyphs imported from Arev Fonts are copyright © Tavmjung Bah.

DejaVu Fonts Copyright and License Agreement

STI Pub Companies

- STIX font

The STIX font is copyright © 2001-2010 by the STI Pub Companies, with portions copyright © 1998-2003 by Micro-Press, Inc. and copyright © 1990 by Elsevier, Inc.

STIX Font License

The STIX Fonts Project

SIL Open Font License Version 1.1

MapleSim Open Source

MapleSim uses portions of the following technologies:

jME

- **jME** (<http://www.jmonkeyengine.org>), which is distributed under the terms of the **Berkeley Software Distribution** (BSD) license.

jME BSD License

Copyright © 2003-2010 jMonkeyEngine

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of 'jMonkeyEngine' nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Lightweight Java Game Library

- **Lightweight Java Game Library** (<http://www.lwjgll.org>), which is distributed under the terms of the **Berkeley Software Distribution** (BSD) license.

Lightweight Java Game Library BSD License

Copyright © 2002-2010 Lightweight Java Game Library Project

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer

- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of 'Light Weight Java Game Library' nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,

EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

FFmpeg

- **FFmpeg** (<http://www.ffmpeg.org>), which is distributed under the terms of the **GNU Lesser General Public License Version 2.1** license.

The **FFmpeg** library is distributed under the terms of the **GNU Lesser General Public License Version 2.1**. In accordance with this license, we are making the version of the **FFmpeg** source code that MapleSim uses available for download at <http://www.maplesoft.com/support/downloads/source/>. A copy of the license file is included (see "COPYING.LIB").

GNU License Agreement

<http://www.gnu.org/licenses/old-licenses/lgpl-2.1.html>

GNU LESSER GENERAL PUBLIC LICENSE

Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc.

51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish);

that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

- **a)** The modified work must itself be a software library.
- **b)** You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.
- **c)** You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.
- **d)** If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.

If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.

5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright

notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

- **a)** Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)
- **b)** Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.
- **c)** Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.
- **d)** If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.
- **e)** Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:

- **a)** Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.
- **b)** Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.

10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions.

You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.

11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL,

INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Libraries

If you develop a new library, and you want it to be of the greatest possible use to the public, we recommend making it free software that everyone can redistribute and change. You can do so by permitting redistribution under these terms (or, alternatively, under the terms of the ordinary General Public License).

To apply these terms, attach the following notices to the library. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

one line to give the library's name and an idea of what it does.

Copyright (C) year name of author

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the library, if necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the library 'Frob' (a library for tweaking knobs) written by James Random Hacker.

signature of Ty Coon, 1 April 1990

Ty Coon, President of Vice

That's all there is to it!

WebM

- **WebM** (<http://www.webmproject.org>), which is distributed under the terms of the **Berkeley Software Distribution** (BSD) licence.

WebM BSD License

Copyright (c) 2010, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Google nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Index

A

Adding Content to MapleSim Server, 3

C

Content Delivery Network, 6, 24

CORS, 7

Example, 25

D

Data Limit for Java Operations, 11

docker compose file, 2

Docker Container, v

information

where to find, v

docker run command, 1

docker stack command, 2

Document Hosting, 3

E

Enable Directory Listings, 6, 23

Endpoints

Compute, 7

Document, 7

Download, 7

Help, 7

Upload, 7

Environment Variables

Base URL for JavaScript Library, 6

Compute Engine, 11

Disabling Security, 11

Specify CPU Limit, 11

Specify Data Limit, 11

Specify Data Limit, Example, 25

Specifying Extra Command Line Arguments, 11

Configuration Logging, 11

Disabling Logging, 11

Flushing Logs, 11

Specify Log File, 11

Specifying Logging Level, 11

Using Synchronous Logging, 11

Content Delivery Network, 6

CORS

Allow Headers Header, 7

Allow Methods Header, 7

Allow Origin Header, 7

Cross-origin Resource Sharing, 7

Directory Listings, 6

Document Engine, 13

CPU Limit, 13

CPU Limit, Example, 27

Data Limit, 13

Data Limit, Example, 27

Disabling Maple Access to Operating System, 13

Specifying Command Line Arguments, 13

Enable Compute Endpoint, 7

Example, 27

Enable Document Endpoint, 7

Enable Download Endpoint, 7

Enable Help Endpoint, 7

Example, 27

Enable sendfile Command, 6

Enable Upload Endpoints, 7

File Not Found, 5

Injecting String into HTML Page Sent to Client, 8

Licensing, 5

Managing Server Connections, 5

Maple Configuration, 10

MapleNet Web Server Endpoints, 7

Mapping Help Links in Worksheets to Webpages, 8

Maximum Number of Maple Engines, 9

Maximum Number of Maple Engines for Image Plot

Generation, 9

Maximum Number of Threads Used for Accepting

Connections, 5

Overview, 5

Port for New Connections, 5

Set Client Configuration Values, 8

Setting Maple libname Variable, 10

Setting Maximum Number of Running Engines, 9

Setting Queue Time Limit, 9

Setting Time Limit for Computations Related to Open

Document, 9

Setting Time Limit for Compute Requests, 9

Example, 25

Setting up content directories, 5

Specify Java Data Limit, 11

Specify the File that Should be Executed When Starting

Maple Engine, 10

SSL, 8

Certificate Authority Path, 8

Check for Certificates, 8

Cypher List, 8

Default Values for Certificate Authority Path and

File, 8

Specify Certificate Authority File, 8

Specify Minimum SSL Protocol Version Accepted,

8

Specify the Maximum Depth of a Certificate Author-

ity File, 8

Verify Connecting Clients Have Valid Signed Certi-

ificate, 8

Web Server Request Timeouts, 5

Worksheet Template Location, 6

Example Configurations

- Basic Compute Hosting, 25
- Content Delivery Network, 24
- CORS, 25
- Document Hosting, 23
- Mounting as a subdirectory of webroot, 23
- Mounting on top of webroot, 24
- Overview, 23
- Security Options, 27

M

Managing MapleNet Server Connections

- Environment Variables, 5

MapleSim Server Basics, 1

Metrics and Monitoring

- Health Check, 17

Metrics

- Prometheus, 19

Monitoring, 18

Metrics and Monitoring Tools, 21

Mounting host directory as a subdirectory of webroot, 23

Mounting host directory into Docker container, 23

Mounting host directory on top of webroot, 24

R

Replacing the MapleSim Server Landing Page, 3

S

Security Issues, 15

Set MathJax Version, 8

Starting MapleSim Server, 1

- docker run command, 1

Starting the MapleSim Server

- docker compose file, 2

Stopping MapleSim Server, 3

Storing cache files, 5

T

Troubleshooting

- Docker not starting, 28
- MapleNet not starting, 28
- Overview, 29
- Performance Issues, 29
- Time out errors, 29

Trusted Users, 15

U

Untrusted Users, 15

W

webroot directory, 5